
mdfreader Documentation

Release 1.4

Aymeric Rateau

April 26, 2016

CONTENTS

1	mdf module documentation	3
1.1	Platform and python version	3
1.2	Dependencies	3
1.3	mdf module	3
2	mdfreader module documentation	9
2.1	Platform and python version	9
2.2	Dependencies	9
2.3	Attributes	9
2.4	mdfreader module	10
3	mdf3reader module documentation	17
3.1	Platform and python version	17
3.2	Dependencies	17
3.3	Attributes	17
3.4	mdf3reader module	17
4	mdfinfo3 module documentation	25
4.1	Platform and python version	25
4.2	Dependencies	25
4.3	Attributes	25
4.4	mdfinfo3 module	25
5	mdf4reader module documentation	29
5.1	Platform and python version	29
5.2	Dependencies	29
5.3	Attributes	29
5.4	mdf4reader module	29
6	mdfinfo4 module documentation	41
6.1	Platform and python version	41
6.2	Dependencies	41
6.3	Attributes	41
6.4	mdfinfo4 module	41
7	Indices and tables	49
	Python Module Index	51
	Index	53

Contents:

MDF MODULE DOCUMENTATION

mdf_skeleton module describing basic mdf structure and methods

Created on Thu Sept 24 2015

Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>

mdf module

```
class mdf.mdf_skeleton (fileName=None, channelList=None, convertAfterRead=True, filterChannel-  
Names=False)
```

Bases: dict

mdf_skeleton class

Attributes

fileName	(str) file name
MDFVersionNumber	(int) mdf file version number
master-Channel-List	(dict) Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.
multiProc	(bool) Flag to request channel conversion multi processed for performance improvement. One thread per data group.
convertAfterRead	(bool) flag to convert raw data to physical just after read
filterChannelNames	(bool) flag to filter long channel names from its module names separated by ‘.’
file_metadata	(dict) file metadata with minimum keys : author, organisation, project, subject, comment, time, date

Methods

add_channel(channel_name, data, master_channel, master_type=1, unit='', description='', conversion=None)	adds channel to mdf dict
remove_channel(channel_name)	removes channel from mdf dict and returns its content
copy()	copy a mdf class
add_metadata(author, organisation, project, subject, comment, date, time)	adds basic metadata from file

add_channel (*dataGroup*, *channel_name*, *data*, *master_channel*, *master_type*=1, *unit*='', *description*='', *conversion*=None)
adds channel to mdf dict.

Parameters *dataGroup* : int

dataGroup number. Is appended to master name for non unique channel names

channel_name : str

channel name

data : numpy array

numpy array of channel's data

master_channel : str

master channel name

master_type : int, optional

master channel type : 0=None, 1=Time, 2=Angle, 3=Distance, 4=index

unit : str, optional

unit description

description : str, optional

channel description

conversion : info class, optional

conversion description from info class

add_metadata (*author*='', *organisation*='', *project*='', *subject*='', *comment*='', *date*='', *time*='')

adds basic metadata to mdf class

Parameters **author** : str

author of file

organisation : str

organisation of author

project : str

subject : str

comment : str

date : str

time : str

copy ()

copy a mdf class

getChannel (*channelName*)

Extract channel dict from mdf structure

Parameters **channelName** : str

channel name

Returns channel dictionary containing data, description, unit, etc.

getChannelConversion (*channelName*)

Extract channel conversion dict from mdf structure

Parameters **channelName** : str

channel name

Returns channel conversion dict

getChannelDesc (*channelName*)

Extract channel description information from mdf structure

Parameters **channelName** : str

channel name

Returns channel description string

getChannelMaster (*channelName*)

Extract channel master name from mdf structure

Parameters **channelName** : str

channel name

Returns channel master name string

getChannelMasterType (*channelName*)

Extract channel master type information from mdf structure

Parameters **channelName** : str

channel name

Returns channel mater type integer

getChannelUnit (*channelName*)

Returns channel unit string Implemented for a future integration of pint

Parameters **channelName** : str

channel name

Returns str

unit string description

remove_channel (*channel_name*)

removes channel from mdf dict.

Parameters **channel_name** : str

channel name

Returns value of mdf dict key=channel_name

remove_channel_conversion (*channelName*)

removes conversion key from mdf channel dict.

Parameters **channelName** : str

channel name

Returns removed value from dict

setChannelAttachment (*channelName, attachment*)

Modifies channel attachment

Parameters **channelName** : str

channel name

attachment

channel attachment

setChannelConversion (*channelName, conversion*)

Modifies conversion dict of channel

Parameters **channelName** : str

channel name

conversion : dict

conversion dictionnary

setChannelData (*channelName, data*)

Modifies data of channel

Parameters **channelName** : str

channel name

data : numpy array

channel data

setChannelDesc (*channelName, desc*)

Modifies description of channel

Parameters `channelName` : str

channel name

desc : str

channel description

setChannelMaster (*channelName*, *master*)

Modifies channel master name

Parameters `channelName` : str

channel name

master : str

master channel name

setChannelMasterType (*channelName*, *masterType*)

Modifies master channel type

Parameters `channelName` : str

channel name

masterType : int

master channel type

setChannelUnit (*channelName*, *unit*)

Modifies unit of channel

Parameters `channelName` : str

channel name

unit : str

channel unit

MDFREADER MODULE DOCUMENTATION

Measured Data Format file reader main module

Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Created on Sun Oct 10 12:57:28 2010

Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>
- Sympy to convert channels with formula
- bitarray for not byte aligned data parsing
- Matplotlib >1.0 <<http://matplotlib.sourceforge.net>>
- NetCDF
- h5py for the HDF5 export
- xlwt for the excel export (not existing for python3)
- openpyxl for the excel 2007 export
- scipy for the Matlab file conversion
- zlib to uncompress data block if needed

Attributes

PythonVersion [float] Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

mdfreader module

```
class mdfreader.mdf (fileName=None,  channelList=None,  convertAfterRead=True,  filterChannel-
                    Names=False)
Bases: mdf3reader.mdf3, mdf4reader.mdf4
mdf class
```

Notes

mdf class is a nested dict Channel name is the primary dict key of mdf class At a higher level, each channel includes the following keys :

- ‘data’ : containing vector of data (numpy)
- ‘unit’ : unit (string)
- ‘master’ : master channel of channel (time, crank angle, etc.)
- ‘description’ : Description of channel
- ‘conversion’: **mdfinfo nested dict for CCBlock.** Exist if channel not converted, used to convert with getChannelData method

Examples

```
>>> import mdfreader
>>> yop=mdfreader.mdf('NameOfFile')
>>> yop.keys() # list channels names
>>> yop.masterChannelList() # list channels grouped by raster or master channel
>>> yop.plot('channelName') or yop.plot({'channel1','channel2'})
>>> yop.resample(0.1) or yop.resample(channelName='master3')
>>> yop.exporttoCSV(sampling=0.01)
>>> yop.exportNetCDF()
>>> yop.exporttoHDF5()
>>> yop.exporttoMatlab()
>>> yop.exporttoExcel()
>>> yop.exporttoXlsx()
>>> yop.convertToPandas() # converts data groups into pandas dataframes
>>> yop.keepChannels({'channel1','channel2','channel3'}) # drops all the channels except the one
>>> yop.getChannelData('channelName') # returns channel numpy array
```

Attributes

fileName	(str) file name
MDFVersionNumber	(int) mdf file version number
master-Channel-List	(dict) Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.
multiProc	(bool) Flag to request channel conversion multi processed for performance improvement. One thread per data group.
file_metadata	(dict) file metadata with minimum keys : author, organisation, project, subject, comment, time, date

Methods

<code>read(fileName = None, multiProc = False, channelList=None, convertAfterRead=True, filterChannelNames=False)</code>	reads mdf file version 3.x and 4.x
<code>write(fileName=None)</code>	writes simple mdf 3.3 file
<code>getChannelData(channelName)</code>	returns channel numpy array
<code>convertAllChannel()</code>	converts all channel data according to CCBLOCK information
<code>getChannelUnit(channelName)</code>	returns channel unit
<code>plot(channels)</code>	Plot channels with Matplotlib
<code>resample(samplingTime = 0.1, masterChannel=None)</code>	Resamples all data groups
<code>exportToCSV(filename = None, sampling = 0.1)</code>	Exports mdf data into CSV file
<code>exportToNetCDF(filename = None, sampling = None)</code>	Exports mdf data into netcdf file
<code>exportToHDF5(filename = None, sampling = None)</code>	Exports mdf class data structure into hdf5 file
<code>exportToMatlab(filename = None)</code>	Exports mdf class data structure into Matlab file
<code>exportToExcel(filename = None)</code>	Exports mdf data into excel 95 to 2003 file
<code>exportToXlsx(filename=None)</code>	Exports mdf data into excel 2007 and 2010 file
<code>convertToPandas(sampling=None)</code>	converts mdf data structure into pandas dataframe(s)
<code>keepChannels(channelList)</code>	keeps only list of channels and removes the other channels
<code>mergeMdf(mdfClass):</code>	Merges data of 2 mdf classes

allPlot ()

convertAllChannel ()

Converts all channels from raw data to converted data according to CCBLOCK information Converted data will take more memory.

convertToPandas (sampling=None)

converts mdf data structure into pandas dataframe(s)

Parameters sampling : float, optional

resampling interval

Notes

One pandas dataframe is converted per data group Not adapted yet for mdf4 as it considers only time master channels

exportToCSV (filename=None, sampling=None)

Exports mdf data into CSV file

Parameters filename : str, optional

file name. If no name defined, it will use original mdf name and path

sampling : float, optional

sampling interval. None by default

Notes

Data saved in CSV file be automatically resampled as it is difficult to save in this format data not sharing same master channel Warning: this can be slow for big data, CSV is text format after all

exportToExcel (*filename=None*)

Exports mdf data into excel 95 to 2003 file

Parameters filename : str, optional

file name. If no name defined, it will use original mdf name and path

Notes

xlwt is not fast for even for small files, consider other binary formats like HDF5 or Matlab If there are more than 256 channels, data will be saved over different worksheets Also Excel 203 is becoming rare these days

exportToHDF5 (*filename=None, sampling=None*)

Exports mdf class data structure into hdf5 file

Parameters filename : str, optional

file name. If no name defined, it will use original mdf name and path

sampling : float, optional

sampling interval.

Notes

The maximum attributes will be stored Data structure will be similar has it is in masterChannelList attribute

exportToMatlab (*filename=None*)

Export mdf data into Matlab file format 5, tentatively compressed

Parameters filename : str, optional

file name. If no name defined, it will use original mdf name and path

Notes

This method will dump all data into Matlab file but you will loose below information: - unit and descriptions of channel - data structure, what is corresponding master channel to a channel. Channels might have then different lengths

exportToNetCDF (*filename=None, sampling=None*)

Exports mdf data into netcdf file

Parameters filename : str, optional

file name. If no name defined, it will use original mdf name and path

sampling : float, optional

sampling interval.

exportToXlsx (*filename=None*)

Exports mdf data into excel 2007 and 2010 file

Parameters **filename** : str, optional

file name. If no name defined, it will use original mdf name and path

Notes

It is recommended to export resampled data for performances

getChannelData (*channelName*)

Return channel numpy array

Parameters **channelName** : str

channel name

Notes

This method is the safest to get channel data as numpy array from 'data' dict key might contain raw data

keepChannels (*channelList*)

keeps only list of channels and removes the other channels

Parameters **channelList** : list of str

list of channel names

mergeMdf (*mdfClass*)

Merges data of 2 mdf classes

Parameters **mdfClass** : mdf

mdf class instance to be merge with self

Notes

both classes must have been resampled, otherwise, impossible to know master channel to match create union of both channel lists and fill with Nan for unknown sections in channels

plot (*channels*)

Plot channels with Matplotlib

Parameters **channels** : str or list of str

channel name or list of channel names

Notes

Channel description and unit will be tentatively displayed with axis labels

read (*fileName=None, multiProc=False, channelList=None, convertAfterRead=True, filterChannelNames=False*)

reads mdf file version 3.x and 4.x

Parameters **fileName** : str, optional

file name

multiProc : bool

flag to activate multiprocessing of channel data conversion

channelList : list of str, optional

list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files

convertAfterRead : bool, optional

flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method `.getChannelData()`

filterChannelNames : bool, optional

flag to filter long channel names from its module names separated by ‘.’

Notes

If you keep convertAfterRead to true, you can set attribute `mdf.multiProc` to activate channel conversion in multiprocessing. Gain in reading time can be around 30% if file is big and using a lot of float channels

resample (*samplingTime=None, masterChannel=None*)

Resamples all data groups into one data group having defined sampling interval or sharing same master channel

Parameters **samplingTime** : float, optional

resampling interval, None by default. If None, will merge all datagroups into a unique datagroup having the highest sampling rate from all datagroups

****or****

masterChannel : str, optional

master channel name to be used for all channels

Notes

1. resampling is relatively safe for mdf3 as it contains only time series. However, mdf4 can contain also distance, angle, etc. It might make not sense to apply one resampling to several data groups that do not share same kind of master channel (like time resampling to distance or angle data groups) If several kind of data groups are used, you should better use pandas to resample

2. resampling will convert all your channels so be careful for big files and memory consumption

write (*fileName=None*)

Writes simple mdf 3.3 file

Parameters **fileName** : str, optional

Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension

Notes

All channels will be converted, so size might be bigger than original file

class `mdfreader.mdfinfo` (*fileName=None, filterChannelNames=False*)

Bases: dict

MDFINFO is a class gathering information from block headers in a MDF (Measure Data Format) file

Structure is nested dicts. Primary key is Block type, then data group, channel group and channel number.

Examples of dicts

- mdfinfo['HDBlock'] header block
- mdfinfo['DGBlock'][dataGroup] Data Group block
- mdfinfo['CGBlock'][dataGroup][channelGroup] Channel Group block
- mdfinfo['CNBlock'][dataGroup][channelGroup][channel] Channel block including text blocks for comment and identifier
- mdfinfo['CCBlock'][dataGroup][channelGroup][channel] Channel conversion information

Examples

```
>>> import mdfreader
>>> FILENAME='toto.dat'
>>> yop=mdfreader.mdfinfo(FILENAME)
or if you are just interested to have only list of channels
>>> yop=mdfreader.mdfinfo() # creates new instance f mdfinfo class
>>> yop=mdfreader.listChannels(FILENAME) # returns a simple list of channel names
```

Attributes

fileName	(str) file name
mdfversion	(int) mdf file version number

Methods

readinfo(fileName = None, filterChannelNames=False)	Reads MDF file and extracts its complete structure
listChannels(fileName = None)	Read MDF file blocks and returns a list of contained channels

listChannels (fileName=None)

Read MDF file blocks and returns a list of contained channels

Parameters **fileName** : string

file name

Returns **nameList** : list of string

list of channel names

readinfo (fileName=None, filterChannelNames=False)

Reads MDF file and extracts its complete structure

Parameters **fileName** : str, optional

file name. If not input, uses fileName attribute

filterChannelNames : bool, optional

flag to filter long channel names including module names separated by a '.'

MDF3READER MODULE DOCUMENTATION

Measured Data Format file reader module for version 3.x

Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Created on Sun Oct 10 12:57:28 2010

Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>
- Sympy to convert channels with formula

Attributes

PythonVersion [float] Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

mdf3reader module

class `mdf3reader.DATA` (*fid, pointer*)
Bases: `dict`

DATA class is organizing record classes itself made of recordchannel. This class inherits from dict. Keys are corresponding to channel group recordID A DATA class corresponds to a data block, a dict of record classes (one per channel group) Each record class contains a list of recordchannel class representing the structure of channel record.

Attributes

<code>fid</code>	(io.open) file identifier
<code>pointerToData</code>	(int) position of Data block in mdf file

Methods

<code>addRecord(record)</code>	Adds a new record in DATA class dict
<code>read(channelList, zip=None)</code>	Reads data block
<code>loadSorted(record, zip=None, nameList=None)</code>	Reads sorted data block from record definition
<code>load(nameList=None)</code>	Reads unsorted data block, not yet implemented

addRecord (*record*)

Adds a new record in DATA class dict

Parameters **record** class

channel group definition listing record channel classes

load (*nameList=None*)

not yet implemented

loadSorted (*record, zip=None, nameList=None*)

Reads sorted data block from record definition

Parameters **record** class

channel group definition listing record channel classes

zip : bool, optional

flag to track if data block is compressed

channelList : list of str, optional

list of channel names

Returns numpy recarray of data

read (*channelList, zip=None*)

Reads data block

Parameters **channelList** : list of str, optional

list of channel names

zip : bool, optional

flag to track if data block is compressed

`mdf3reader.expConv` (*data, conv*)

apply exponential conversion to data

Parameters **data** : numpy 1D array

raw data to be converted to physical value

conv : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf3reader.formulaConv` (*data, conv*)

apply formula conversion to data

Parameters **data** : numpy 1D array

raw data to be converted to physical value

conv : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

Notes

Requires sympy module

`mdf3reader.linearConv(data, conv)`

apply linear conversion to data

Parameters `data` : numpy 1D array

raw data to be converted to physical value

`conv` : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf3reader.logConv(data, conv)`

apply logarithmic conversion to data

Parameters `data` : numpy 1D array

raw data to be converted to physical value

`conv` : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

class `mdf3reader.mdf3` (*fileName=None, channelList=None, convertAfterRead=True, filterChannelNames=False*)

Bases: `mdf.mdf_skeleton`

mdf file version 3.0 to 3.3 class

Attributes

<code>fileName</code>	(str) file name
<code>MDFVersionNumber</code>	(int) mdf file version number
<code>masterChannelList</code>	(dict) Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.
<code>multiProc</code>	(bool) Flag to request channel conversion multi processed for performance improvement. One thread per data group.
<code>convertAfterRead</code>	(bool) flag to convert raw data to physical just after read
<code>filterChannelNames</code>	(bool) flag to filter long channel names from its module names separated by '.'
<code>file_metadata</code>	(dict) file metadata with minimum keys : author, organisation, project, subject, comment, time, date

Methods

<code>read3(fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True)</code>	Reads mdf 3.x file data and stores it in dict
<code>_getChannelData3(channelName)</code>	Returns channel numpy array
<code>_convertChannel3(channelName)</code>	converts specific channel from raw to physical data according to CCBlock information
<code>_convertAllChannel3()</code>	Converts all channels from raw data to converted data according to CCBlock information
<code>write3(fileName=None)</code>	Writes simple mdf 3.3 file

read3 (*fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True, filterChannelNames=False*)

Reads mdf 3.x file data and stores it in dict

Parameters **fileName** : str, optional

file name

info : mdfinfo3.info3 class

info3 class containing all MDF Blocks

multiProc : bool

flag to activate multiprocessing of channel data conversion

channelList : list of str, optional

list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files

convertAfterRead : bool, optional

flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method `.getChannelData()`

write3 (*fileName=None*)

Writes simple mdf 3.3 file

Parameters **fileName** : str, optional

Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension

Notes

All channels will be converted to physical data, so size might be bigger than original file

`mdf3reader.polyConv(data, conv)`

apply polynomial conversion to data

Parameters **data** : numpy 1D array

raw data to be converted to physical value

conv : mdfinfo3.info3 conversion block (‘CCBlock’) dict

Returns converted data to physical value

`mdf3reader.rationalConv(data, conv)`

apply rational conversion to data

Parameters `data` : numpy 1D array

raw data to be converted to physical value

`conv` : `mdfinfo3.info3` conversion block ('CCBlock') dict

Returns converted data to physical value

class `mdf3reader.record(dataGroup, channelGroup)`

Bases: `list`

record class lists recordchannel classes, it is representing a channel group

Attributes

<code>recordLength</code>	(int) length of record corresponding of channel group in Byte
<code>numberOfRecords</code>	(int) number of records in data block
<code>recordID</code>	(int) recordID corresponding to channel group
<code>recordIDsize</code>	(int) size of recordID
<code>dataGroup</code>	(int:) data group number
<code>channelGroup</code>	(int) channel group number
<code>numpyDataRecordFormat</code>	(list) list of numpy (dtype) for each channel
<code>dataRecordName</code>	(list) list of channel names used for recarray attribute definition
<code>master</code>	(dict) define name and number of master channel
<code>recordToChannelMatching</code>	(dict) helps to identify nested bits in byte
<code>channelNames</code>	(list) channel names to be stored, useful for low memory consumption but slow

Methods

<code>addChannel(info, channelNumber)</code>	
<code>loadInfo(info)</code>	
<code>readSortedRecord(fid, pointer, channelList=None)</code>	
<code>readUnsortedRecord(buf, channelList=None)</code>	

addChannel (*info*, *channelNumber*)

add a channel in class

Parameters `info` : `mdfinfo3.info3` class

`channelNumber` : int

channel number in `mdfinfo3.info3` class

loadInfo (*info*)

gathers records related from info class

Parameters `info` : `mdfinfo3.info3` class

readSortedRecord (*fid*, *pointer*, *channelList=None*)

reads record, only one channel group per datagroup

Parameters `fid` : float

file identifier

pointer

position in file of data block beginning

channelList : list of str, optional

list of channel to read

Returns **rec** : numpy recarray

contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Notes

If channelList is None, read data using `numpy.core.records.fromfile` that is rather quick. However, in case of large file, you can use channelList to load only interesting channels or only one channel on demand, but be aware it might be much slower.

readUnsortedRecord (*buf, channelList=None*)

Not implemented yet, no reference files available to test it

class `mdf3reader.recordChannel` (*info, dataGroup, channelGroup, channelNumber, recordIDsize*)

recordChannel class gathers all about channel structure in a record

Attributes

name	(str) Name of channel
unit	(str, default empty string) channel unit
desc	(str) channel description
conversion	(info class) conversion dictionnary
channelNumber	(int) channel number corresponding to <code>mdfinfo3.info3</code> class
signal-DataType	(int) signal type according to specification
bitCount	(int) number of bits used to store channel record
nBytes	(int) number of bytes (1 byte = 8 bits) taken by channel record
dataFormat	(str) numpy dtype as string
CFormat	(struct class instance) struct instance to convert from C Format
byteOffset	(int) position of channel record in complete record in bytes
bitOffset	(int) bit position of channel value inside byte in case of channel having bit count below 8
RecordFormat	(list of str) dtype format used for <code>numpy.core.records</code> functions ((name,name_title),str_type)
channelType	(int) channel type
posBeg	(int) start position in number of bit of channel record in complete record
posEnd	(int) end position in number of bit of channel record in complete record

Methods

<code>__init__(info, dataGroup, channelGroup, channelNumber, recordIDsize)</code>	constructor
<code>__str__()</code>	to print class attributes

`mdf3reader.tabConv` (*data, conv*)

apply Tabular conversion to data

Parameters **data** : numpy 1D array

raw data to be converted to physical value

conv : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf3reader.tabInterpConv(data, conv)`

apply Tabular interpolation conversion to data

Parameters **data** : numpy 1D array

raw data to be converted to physical value

conv : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf3reader.textRangeTableConv(data, conv)`

apply text range table conversion to data

Parameters **data** : numpy 1D array

raw data to be converted to physical value

conv : mdfinfo3.info3 conversion block ('CCBlock') dict

Returns converted data to physical value

MDFINFO3 MODULE DOCUMENTATION

Measured Data Format blocks parser for version 3.x

Created on Thu Dec 9 12:57:28 2014

Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>

Attributes

PythonVersion [float] Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

mdfinfo3 module

class `mdfinfo3.info3` (*fileName=None, fid=None, filterChannelNames=False*)

Bases: dict

mdf file info class version 3.x MDFINFO is a class information about an MDF (Measure Data Format) file
Based on following specification <http://powertrainnvh.com/nvh/MDFspecificationv03.pdf>

Notes

`mdfinfo(FILENAME)` contains a dict of structures, for each data group, containing key information about all channels in each group. FILENAME is a string that specifies the name of the MDF file. General dictionary structure is the following

- `mdfinfo['HDBlock']` header block

- `mdfinfo['DGBlock']`[dataGroup] Data Group block
- `mdfinfo['CGBlock']`[dataGroup][channelGroup] Channel Group block
- `mdfinfo['CNBlock']`[dataGroup][channelGroup][channel] Channel block including text blocks for comment and identifier
- `mdfinfo['CCBlock']`[dataGroup][channelGroup][channel] Channel conversion information

Attributes

<code>filterChannel-Names</code>	(bool, optional) flag to filter long channel names including module names separated by a '.'
<code>fileName</code>	(str) name of file

Methods

static `blockformats3` (*block*, *version=0*)

This function returns all the predefined formats for the different blocks in the MDF file

Parameters **block** : str

kind of block

version : int

mdf version

Returns nested list of str and int describing structure of block to be used by `mdfblockread3` method

listChannels3 (*fileName=None*)

reads data, channel group and channel blocks to list channel names

Returns list of channel names

Attributes

<code>fileName</code>	(str) file name
-----------------------	-----------------

static `mdfblockread3` (*blockFormat*, *fid*, *pointer*, *removeTrailing0=True*)

Extract block of data from MDF file in original data types. Returns a dictionary with keys specified in data structure `blockFormat`

Parameters **blockFormat** : nested list

output of `blockformats3` method

fid : float

file identifier

pointer : int

position of block in file

removeTrailing0 : bool, optional

removes or not the trailing 0 from strings

Returns Block content in a dict

readinfo3 (*fid*)

read all file blocks except data

Parameters **fid** : float

file identifier

MDF4READER MODULE DOCUMENTATION

Measured Data Format file reader module for version 4.x.

Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Created on Thu Dec 10 12:57:28 2013

Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>
- bitarray to parse bits in not aligned bytes
- Sympy to convert channels with formula if needed
- zlib to uncompress data block if needed

Attributes

PythonVersion [float] Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

mdf4reader module

class `mdf4reader.DATA` (*fid, pointer*)
Bases: `dict`

DATA class is organizing record classes itself made of channel class. This class inherits from dict. Keys are corresponding to channel group recordID A DATA class corresponds to a data block, a dict of record classes (one per channel group) Each record class contains a list of channel class representing the structure of channel record.

Attributes

fid	(io.open) file identifier
pointerToData	(int) position of Data block in mdf file
type	(str) 'sorted' or 'unsorted' data block

Methods

addRecord(record)	Adds a new record in DATA class dict
read(channelList, zip=None)	Reads data block
load(record, zip=None, nameList=None)	Reads sorted data block from record definition
readRecord(recordID, buf, channelList=None):	read record from a buffer

addRecord (*record*)

Adds a new record in DATA class dict.

Parameters **record** class

channel group definition listing record channel classes

load (*record*, *zip=None*, *nameList=None*, *sortedFlag=True*)

Reads data block from record definition

Parameters **record** class

channel group definition listing record channel classes

zip : bool, optional

flag to track if data block is compressed

nameList : list of str, optional

list of channel names

Returns numpy recarray of data

read (*channelList*, *zip=None*)

Reads data block

Parameters **channelList** : list of str

list of channel names

zip : bool, optional

flag to track if data block is compressed

readRecord (*recordID*, *buf*, *channelList=None*)

read record from a buffer

Parameters **recordID** : int

record identifier

buf : str

buffer of data from file to be converted to channel raw data

channelList : list of str

list of channel names to be read

`mdf4reader.DATABlock (record, parent_block, channelList=None, sortedFlag=True)`

DATABlock converts raw data into arrays

Parameters `record` : class

record class instance describing a channel group record

`parent_block` : class

MDFBlock class containing at least parent block header

`channelList` : list of str, optional

defines list of channels to only read, can be slow but saves memory, for big files

`sortedFlag` : bool, optional

flag to know if data block is sorted (only one Channel Group in block) or unsorted (several Channel Groups identified by a recordID). As unsorted block can contain CG records in random order, block is processed iteratively, not in raw like sorted -> much slower reading

Returns a recarray containing the channels data

Notes

This function will read DTBlock, RDBlock, DZBlock (compressed), RDBlock (VLSD), sorted or unsorted

`mdf4reader.append_field (rec, name, arr, numpy_dtype=None)`

append new field in a recarray

Parameters `rec` : numpy recarray

`name` : str

name of field to be appended

`arr` : numpy array to be appended

`numpy_dtype` : numpy dtype, optional

apply same dtype as arr by default but can be modified

Returns numpy recarray appended

`mdf4reader.arrayformat4 (signalDataType, numberOfBits)`

function returning numpy style string from channel data type and number of bits

Parameters `signalDataType` : int

channel data type according to specification

`numberOfBits` : int

number of bits taken by channel data in a record

Returns `dataType` : str

numpy dtype format used by `numpy.core.records` to read channel raw data

`mdf4reader.bits_to_bytes (nBits)`

Converts number of bits into number of aligned bytes

Parameters `nBits` : int

number of bits

Returns number of equivalent bytes

`mdf4reader.change_field_name(arr, old_name, new_name)`
modifies name of field in a recarray

Parameters `arr` : numpy recarray

old_name : str

old field

new_name : str

new field

Returns numpy recarray with modified field name

class `mdf4reader.channel`
channel class gathers all about channel structure in a record

Attributes

<code>name</code>	(str) Name of channel
<code>unit</code>	(str, default empty string) channel unit
<code>desc</code>	(str) channel description
<code>type</code>	(str) channel type. Can be 'standard', 'CANOpen' or 'InvalidBytes'
<code>conversion</code>	(info class) conversion dictionnary
<code>channelNum- ber</code>	(int) channel number corresponding to <code>mdfinfo3.info3</code> class
<code>channelGroup</code>	(int) channel group number corresponding to <code>mdfinfo3.info3</code> class
<code>dataGroup</code>	(int) data group number corresponding to <code>mdfinfo3.info3</code> class
<code>signal- DataType</code>	(int) signal type according to specification
<code>bitCount</code>	(int) number of bits used to store channel record
<code>nBytes</code>	(int) number of bytes (1 byte = 8 bits) taken by channel record
<code>dataFormat</code>	(str) numpy dtype as string
<code>Format :</code>	C format understood by <code>fread</code>
<code>CFormat</code>	(struct class instance) struct instance to convert from C Format
<code>byteOffset</code>	(int) position of channel record in complete record in bytes
<code>bitOffset</code>	(int) bit position of channel value inside byte in case of channel having bit count below 8
<code>RecordFormat</code>	(list of str) dtype format used for <code>numpy.core.records</code> functions ((name,name_title),str_type)
<code>channelType</code>	(int) channel type ; 0 fixed length data, 1 VLSD, 2 master, 3 virtual master, 4 sync, 5 MLSD, 6 virtual data
<code>channelSync- Type</code>	(int) channel synchronisation type ; 0 None, 1 Time, 2 Angle, 3 Distance, 4 Index
<code>posByteBeg</code>	(int) start position in number of byte of channel record in complete record
<code>posByteEnd</code>	(int) end position in number of byte of channel record in complete record
<code>posBitBeg</code>	(int) start position in number of bit of channel record in complete record
<code>posBitEnd</code>	(int) end position in number of bit of channel record in complete record
<code>VLSD_CG_Flag</code>	(bool) flag when Channel Group VLSD is used
<code>data</code>	(int) pointer to data block linked to a channel (VLSD, MLSD)

Methods

<code>__init__()</code>	constructor
<code>__str__()</code>	to print class attributes
<code>attachment(fid, info)</code>	in case of sync channel attached
<code>set(info, dataGroup, channelGroup, channelNumber, recordIDsize)</code>	standard channel initialisation
<code>setCANOpen(info, dataGroup, channelGroup, channelNumber, recordIDsize, name)</code>	CANOpen channel initialisation
<code>setInvalidBytes(info, dataGroup, channelGroup, recordIDsize, byte_aligned)</code>	Invalid Bytes channel initialisation

attachment (*fid, info*)

set (*info, dataGroup, channelGroup, channelNumber, recordIDsize*)
standard record channel initialisation

Parameters **info** : mdfinfo4.info4 class

dataGroup : int

data group number in mdfinfo4.info4 class

channelGroup : int

channel group number in mdfinfo4.info4 class

channelNumber : int

channel number in mdfinfo4.info4 class

recordIDsize : int

size of record ID in Bytes

setCANOpen (*info, dataGroup, channelGroup, channelNumber, recordIDsize, name*)
CANOpen channel initialisation

Parameters **info** : mdfinfo4.info4 class

dataGroup : int

data group number in mdfinfo4.info4 class

channelGroup : int

channel group number in mdfinfo4.info4 class

channelNumber : int

channel number in mdfinfo4.info4 class

recordIDsize : int

size of record ID in Bytes

name : str

name of channel. Should be in ('ms', 'day', 'days', 'hour', 'month', 'min', 'year')

setInvalidBytes (*info, dataGroup, channelGroup, recordIDsize, byte_aligned=True*)
invalid_bytes channel initialisation

Parameters **info** : mdfinfo4.info4 class

dataGroup : int

data group number in mdinfo4.info4 class

channelGroup : int

channel group number in mdinfo4.info4 class

channelNumber : int

channel number in mdinfo4.info4 class

recordIDsize : int

size of record ID in Bytes

byte_aligned : Bool

Flag for byte alignment

validity_channel (*channelName*)

extract channel validity bits

Parameters **channelName** : str

channel name

`mdf4reader.convertChannelData4` (*channel*, *channelName*, *convert_tables*, *multiProc=False*,
Q=None)

converts specific channel from raw to physical data according to CCBLOCK information

Parameters **channelName** : dict

channel dict containing keys like 'data', 'unit', 'comment' and potentially 'conversion'
dict

channelName : str

name of channel

convert_tables : bool

activates computation intensive loops for conversion with tables. Default is False

multiProc : bool, default False

flag to put data in multiprocessing queue

Q : Queue class, default None

Queue used for multiprocessing

Returns dict

returns dict with channelName key containing numpy array converted to physical values
according to conversion type

`mdf4reader.convertName` (*channelName*)

Adds '_title' to channel name for numpy.core.records methods.

`mdf4reader.datatypeformat4` (*signalDataType*, *numberOfBits*)

function returning C format string from channel data type and number of bits

Parameters **signalDataType** : int

channel data type according to specification

numberOfBits : int

number of bits taken by channel data in a record

Returns **dataType** : str

C format used by fread to read channel raw data

`mdf4reader.decompress_datablock(block, zip_type, zip_parameter, org_data_length)`
decompress datablock.

Parameters `block` : bytes

raw data compressed

zip_type : int

0 for non transposed, 1 for transposed data

zip_parameter : int

first dimension of matrix to be transposed

org_data_length : int

uncompressed data length

Returns uncompressed raw data

`mdf4reader.equalizeStringLength(buf)`

Makes all strings in a list having same length by appending spaces strings.

Parameters `buf` : list of str

Returns list of str elements all having same length

`mdf4reader.formulaConv(vect, formula)`

apply formula conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

cc_val : `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.linearConv(vect, cc_val)`

apply linear conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

cc_val : `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

class `mdf4reader.mdf4` (`fileName=None`, `channelList=None`, `convertAfterRead=True`, `filterChannelNames=False`)

Bases: `mdf.mdf_skeleton`

mdf file reader class from version 4.0 to 4.1.1

Attributes

fileName	(str) file name
MDFVersionNumber	(int) mdf file version number
masterChannelList	(dict) Represents data structure: a key per master channel with corresponding value containing a list of channels One key or master channel represents then a data group having same sampling interval.
multiProc	(bool) Flag to request channel conversion multi processed for performance improvement. One thread per data group.
convertAfterRead	(bool) flag to convert raw data to physical just after read
filterChannelNames	(bool) flag to filter long channel names from its module names separated by ‘.’
file_metadata	(dict) file metadata with minimum keys : author, organisation, project, subject, comment, time, date

Methods

read4(fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True)	Reads mdf 4.x file data and stores it in dict
_getChannelData4(channelName)	Returns channel numpy array
_convertChannel4(channelName)	converts specific channel from raw to physical data according to CCBlock information
_convertAllChannel4()	Converts all channels from raw data to converted data according to CCBlock information

read4 (*fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True, filterChannelNames=False*)

Reads mdf 4.x file data and stores it in dict

Parameters **fileName** : str, optional

file name

info : mdinfo4.info4 class

info3 class containing all MDF Blocks

multiProc : bool

flag to activate multiprocessing of channel data conversion

channelList : list of str, optional

list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files

convertAfterRead : bool, optional

flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method .getChannelData()

`mdf4reader.rationalConv(vect, cc_val)`

apply rational conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

class `mdf4reader.record(dataGroup, channelGroup)`

Bases: `list`

record class listing channel classes. It is representing a channel group

Attributes

<code>CGrecordLength</code>	(int) length of record corresponding of channel group in Byte CG Block information
<code>recordLength</code>	(int) length of record as understood by program based on C datatypes
<code>numberOfRecords</code>	(int) number of records in data block
<code>recordID</code>	(int) recordID corresponding to channel group
<code>recordIDsize</code>	(int) size of recordID
<code>recordIDCFormat</code>	(str) record identifier C format string as understood by fread
<code>dataGroup</code>	(int:) data group number
<code>channelGroup</code>	(int) channel group number
<code>numpyDataRecordFormat</code>	(list) list of numpy (dtype) for each channel
<code>dataRecordName</code>	(list) list of channel names used for recarray attribute definition
<code>master</code>	(dict) define name and number of master channel
<code>recordToChannelMatching</code>	(dict) helps to identify nested bits in byte
<code>channelNames</code>	(list) channel names to be stored, useful for low memory consumption but slow
<code>Flags</code>	(bool) channel flags as from specification
<code>VLSD_CG</code>	(dict) dict of Channel Group VLSD, key being recordID
<code>VLSD</code>	(list of channel classes) list of channel classes being VLSD
<code>MLSD</code>	(dict) copy from <code>info['MLSD']</code> if existing
<code>byte_aligned</code>	(Bool, True by default) flag for byte aligned record
<code>hiddenBytes</code>	(Bool, False by default) flag in case of non declared channels in record, forces to use <code>readBitarray</code>
<code>invalid_channel</code>	(Default None) <code>invalid_byte</code> class if existing in record otherwise None
<code>CANOpen</code>	(str, Default None) 'time' if record contains CANOpen time channel, same for 'date'
<code>Methods</code>	
<code>addChannel(info, channelNumber)</code>	
<code>loadInfo(info)</code>	
<code>readSortedRecord(fid, pointer, channelList=None)</code>	
<code>readRecordBuf(buf, channelList=None)</code>	
<code>readBitarray(bita, channelList=None)</code>	

Methods

addChannel (*info*, *channelNumber*)

add a channel in class

Parameters **info** : mdinfo4.info4 class

channelNumber : int

channel number in mdinfo4.info4 class

loadInfo (*info*)

gathers records related from info class

Parameters **info** : mdinfo4.info4 class

readBitarray (*bita*, *channelList=None*)

reads stream of record bytes using bitarray module needed for not byte aligned data

Parameters **bita** : stream

stream of bytes

channelList : List of str, optional

list of channel to read

Returns **rec** : numpy recarray

contains a matrix of raw data in a recarray (attributes corresponding to channel name)

readRecordBuf (*buf*, *channelList=None*)

read stream of record bytes

Parameters **buf** : stream

stream of bytes read in file

channelList : list of str, optional

list of channel to read

Returns **rec** : dict

returns dictionary of channel with its corresponding values

readSortedRecord (*fid*, *pointer*, *channelList=None*)

reads record, only one channel group per datagroup

Parameters **fid** : float

file identifier

pointer

position in file of data block beginning

channelList : list of str, optional

list of channel to read

Returns **rec** : numpy recarray

contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Notes

If channelList is None, read data using `numpy.core.records.fromfile` that is rather quick. However, in case of large file, you can use channelList to load only interesting channels or only one channel on demand, but be aware it might be much slower.

`mdf4reader.textToTextConv(vect, cc_ref)`

apply text to text conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_ref` : `cc_ref` from `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.textToValueConv(vect, cc_val, cc_ref)`

apply text to value conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `cc_val` from `mdfinfo4.info4` conversion block ('CCBlock') dict

`cc_ref` : `cc_ref` from `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.valueRangeToTextConv(vect, cc_val, cc_ref)`

apply value range to text conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `cc_val` from `mdfinfo4.info4` conversion block ('CCBlock') dict

`cc_ref` : `cc_ref` from `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.valueRangeToValueTableConv(vect, cc_val)`

apply value range to value table conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.valueToTextConv(vect, cc_val, cc_ref)`

apply value to text conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `cc_val` from `mdfinfo4.info4` conversion block ('CCBlock') dict

`cc_ref` : `cc_ref` from `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.valueToValueTableWInterpConv(vect, cc_val)`
apply value to value table with interpolation conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

`mdf4reader.valueToValueTableWOInterpConv(vect, cc_val)`
apply value to value table without interpolation conversion to data

Parameters `vect` : numpy 1D array

raw data to be converted to physical value

`cc_val` : `mdfinfo4.info4` conversion block ('CCBlock') dict

Returns converted data to physical value

MDFINFO4 MODULE DOCUMENTATION

Measured Data Format blocks parser for version 4.x

Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Created on Sun Dec 15 12:57:28 2013

Author Aymeric Rateau

Dependencies

- Python >2.6, >3.2 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>

Attributes

PythonVersion [float] Python version currently running, needed for compatibility of both python 2.6+ and 3.2+

mdfinfo4 module

class `mdfinfo4.ATBlock` (*fid, pointer*)

Bases: `mdfinfo4.MDFBlock`

reads Attachment block and saves in class dict

Methods

class `mdfinfo4.CABlock` (*fid, pointer*)

Bases: `mdfinfo4.MDFBlock`

reads Channel Array block and saves in class dict

Methods

class `mdfinfo4.CCBlock` (*fid, pointer*)
Bases: `mdfinfo4.MDFBlock`
reads Channel Conversion block and saves in class dict

Methods

class `mdfinfo4.CGBlock` (*fid, pointer*)
Bases: `mdfinfo4.MDFBlock`
reads Channel Group block and saves in class dict

Methods

class `mdfinfo4.CHBlock` (*fid, pointer*)
Bases: `mdfinfo4.MDFBlock`
reads Channel Hierarchy block and saves in class dict

Methods

class `mdfinfo4.CNBlock` (*fid, pointer*)
Bases: `mdfinfo4.MDFBlock`
reads Channel block and saves in class dict

Methods

class `mdfinfo4.CommentBlock` (*fid, pointer, MDType=None*)
Bases: `mdfinfo4.MDFBlock`
reads Comment block and saves in class dict

Notes

Can read xml (MD metadata) or text (TX) comments from several kind of blocks

Methods

extractXmlField (*xml_tree, field*)
Extract Xml field from a xml tree
Parameters `xml_tree` : xml tree from `xml.etree.ElementTree`
field : str
Returns field value in xml tree

class `mdfinfo4.DGBlock` (*fid, pointer*)
 Bases: `mdfinfo4.MDFBlock`
 reads Data Group block and saves in class dict

Methods

class `mdfinfo4.EVBlock` (*fid, pointer*)
 Bases: `mdfinfo4.MDFBlock`
 reads Event block and saves in class dict

Methods

class `mdfinfo4.FHBlock` (*fid, pointer*)
 Bases: `mdfinfo4.MDFBlock`
 reads File History block and save in class dict

Methods

class `mdfinfo4.HDBlock` (*fid, pointer=64*)
 Bases: `mdfinfo4.MDFBlock`
 reads Header block and save in class dict

Methods

class `mdfinfo4.IDBlock` (*fid*)
 Bases: `mdfinfo4.MDFBlock`
 reads ID Block and save in class dict

Methods

class `mdfinfo4.MDFBlock`
 Bases: `dict`
 MDFBlock base class for the MDF related block classes

Methods

<code>loadHeader(fid, pointer)</code>	reads block's header and put in class dict
<code>mdfblockread(fid, type, count)</code>	converts a byte array of length count to a given data type
<code>mdfblockreadCHAR(fid, count)</code>	reads a character chain of length count encoded in latin.
<code>mdfblockreadBYTE(fid, count)</code>	reads an array of UTF-8 encoded bytes

loadHeader (*fid, pointer*)
 reads block's header and put in class dict

Parameters *fid* : float
 file identifier

pointer : int

position of block in file

static mdfblockread (*fid, type, count*)

converts a byte array of length count to a given data type

Parameters **type** : str

C format data type

count : int

number of elements to sequentially read

Returns array of values of 'type' parameter

static mdfblockreadBYTE (*fid, count*)

reads an array of UTF-8 encoded bytes. Removes trailing 0

Parameters **count** : int

number of bytes to read

Returns bytes array of length count

static mdfblockreadCHAR (*fid, count*)

reads a character chain of length count encoded in latin. Removes trailing 0

Parameters **count** : int

number of characters to read

Returns a string of length count

class mdfinfo4.**SIBlock** (*fid, pointer*)

Bases: *mdfinfo4.MDFBlock*

reads Source Information block and saves in class dict

Methods

class mdfinfo4.**SRBlock** (*fid, pointer*)

Bases: *mdfinfo4.MDFBlock*

reads Sample Reduction block and saves in class dict

Methods

mdfinfo4.**elementTreeToDict** (*element*)

converts xml tree into dictionary

Parameters **element** : xml tree from xml.etree.ElementTree

Returns dict of xml tree flattened

class mdfinfo4.**info4** (*fileName=None, fid=None*)

Bases: dict

information block parser fo MDF file version 4.x

Notes

mdfinfo(FILENAME) contains a dict of structures, for each data group, containing key information about all channels in each group. FILENAME is a string that specifies the name of the MDF file. Either file name or fid should be given. General dictionary structure is the following

- mdfinfo['HDBlock'] header block
- mdfinfo['DGBlock'][dataGroup] Data Group block
- mdfinfo['CGBlock'][dataGroup][channelGroup] Channel Group block
- mdfinfo['CNBlock'][dataGroup][channelGroup][channel] Channel block including text blocks for comment and identifier
- mdfinfo['CCBlock'][dataGroup][channelGroup][channel] Channel conversion information

Attributes

fileName	(str) name of file
----------	--------------------

Methods

listChannels4 (*fileName=None*)

Read MDF file and extract its complete structure

Parameters **fileName** : str

file name

Returns list of channel names contained in file

readATBlock (*self, fid, pointer*)

reads Attachment blocks

Parameters **fid** : float

file identifier

pointer : int

position of ATBlock in file

Returns Attachments Blocks in a dict

readCGBlock (*fid, dg, channelNameList=False*)

reads Channel Group blocks

Parameters **fid** : float

file identifier

dg : int

data group number

channelNameList : bool

Flag to reads only channel blocks for listChannels4 method

readCNBlock (*fid, dg, cg, channelNameList=False*)

reads Channel blocks

Parameters **fid** : float

file identifier

dg : int

data group number

cg : int

channel group number in data group

channelNameList : bool

Flag to reads only channel blocks for listChannels4 method

readComposition (*fid, dg, cg, MLSDChannels, channelNameList=False*)

check for composition of channels, arrays or structures

Parameters **fid** : float

file identifier

dg : int

data group number

cg : int

channel group number in data group

MLSDChannels : list of int

channel numbers

channelNameList : bool

Flag to reads only channel blocks for listChannels4 method

Returns MLSDChannels list of appended Maximum Length Sampling Data channels

readDGBlock (*fid, channelNameList=False*)

reads Data Group Blocks

Parameters **fid** : float

file identifier

channelNameList : bool

Flag to reads only channel blocks for listChannels4 method

readSRBlock (*fid, pointer*)

reads Sample Reduction Blocks

Parameters **fid** : float

file identifier

pointer : int

position of SRBlock in file

Returns Sample Reduction Blocks in a dict

readinfo (*fid*)

read all file blocks except data

Parameters **fid** : float

file identifier

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

m

- mdf, 3
- mdf3reader, 17
- mdf4reader, 29
- mdfinfo3, 25
- mdfinfo4, 41
- mdfreader, 9

A

add_channel() (mdf.mdf_skeleton method), 4
 add_metadata() (mdf.mdf_skeleton method), 5
 addChannel() (mdf3reader.record method), 21
 addChannel() (mdf4reader.record method), 38
 addRecord() (mdf3reader.DATA method), 18
 addRecord() (mdf4reader.DATA method), 30
 allPlot() (mdfreader.mdf method), 11
 append_field() (in module mdf4reader), 31
 arrayformat4() (in module mdf4reader), 31
 ATBlock (class in mdinfo4), 41
 attachment() (mdf4reader.channel method), 33

B

bits_to_bytes() (in module mdf4reader), 31
 blockformats3() (mdinfo3.info3 static method), 26

C

CABlock (class in mdinfo4), 41
 CCBBlock (class in mdinfo4), 42
 CGBBlock (class in mdinfo4), 42
 change_field_name() (in module mdf4reader), 32
 channel (class in mdf4reader), 32
 CHBlock (class in mdinfo4), 42
 CNBlock (class in mdinfo4), 42
 CommentBlock (class in mdinfo4), 42
 convertAllChannel() (mdfreader.mdf method), 11
 convertChannelData4() (in module mdf4reader), 34
 convertName() (in module mdf4reader), 34
 convertToPandas() (mdfreader.mdf method), 11
 copy() (mdf.mdf_skeleton method), 5

D

DATA (class in mdf3reader), 17
 DATA (class in mdf4reader), 29
 DATABlock() (in module mdf4reader), 30
 datatypeformat4() (in module mdf4reader), 34
 decompress_datablock() (in module mdf4reader), 35
 DGBBlock (class in mdinfo4), 42

E

elementTreeToDict() (in module mdinfo4), 44

equalizeStringLength() (in module mdf4reader), 35
 EVBlock (class in mdinfo4), 43
 expConv() (in module mdf3reader), 18
 exportToCSV() (mdfreader.mdf method), 11
 exportToExcel() (mdfreader.mdf method), 12
 exportToHDF5() (mdfreader.mdf method), 12
 exportToMatlab() (mdfreader.mdf method), 12
 exportToNetCDF() (mdfreader.mdf method), 12
 exportToXlsx() (mdfreader.mdf method), 12
 extractXmlField() (mdinfo4.CommentBlock method), 42

F

FHBlock (class in mdinfo4), 43
 formulaConv() (in module mdf3reader), 18
 formulaConv() (in module mdf4reader), 35

G

getChannel() (mdf.mdf_skeleton method), 5
 getChannelConversion() (mdf.mdf_skeleton method), 5
 getChannelData() (mdfreader.mdf method), 13
 getChannelDesc() (mdf.mdf_skeleton method), 5
 getChannelMaster() (mdf.mdf_skeleton method), 5
 getChannelMasterType() (mdf.mdf_skeleton method), 5
 getChannelUnit() (mdf.mdf_skeleton method), 6

H

HDBlock (class in mdinfo4), 43

I

IDBlock (class in mdinfo4), 43
 info3 (class in mdinfo3), 25
 info4 (class in mdinfo4), 44

K

keepChannels() (mdfreader.mdf method), 13

L

linearConv() (in module mdf3reader), 19
 linearConv() (in module mdf4reader), 35
 listChannels() (mdfreader.mdinfo method), 15
 listChannels3() (mdinfo3.info3 method), 26
 listChannels4() (mdinfo4.info4 method), 45

load() (mdf3reader.DATA method), 18
load() (mdf4reader.DATA method), 30
loadHeader() (mdfinfo4.MDFBlock method), 43
loadInfo() (mdf3reader.record method), 21
loadInfo() (mdf4reader.record method), 38
loadSorted() (mdf3reader.DATA method), 18
logConv() (in module mdf3reader), 19

M

mdf (class in mdfreader), 10
mdf (module), 3
mdf3 (class in mdf3reader), 19
mdf3reader (module), 17
mdf4 (class in mdf4reader), 35
mdf4reader (module), 29
mdf_skeleton (class in mdf), 3
MDFBlock (class in mdfinfo4), 43
mdfblockread() (mdfinfo4.MDFBlock static method), 44
mdfblockread3() (mdfinfo3.info3 static method), 26
mdfblockreadBYTE() (mdfinfo4.MDFBlock static method), 44
mdfblockreadCHAR() (mdfinfo4.MDFBlock static method), 44
mdfinfo (class in mdfreader), 14
mdfinfo3 (module), 25
mdfinfo4 (module), 41
mdfreader (module), 9
mergeMdf() (mdfreader.mdf method), 13

P

plot() (mdfreader.mdf method), 13
polyConv() (in module mdf3reader), 20

R

rationalConv() (in module mdf3reader), 20
rationalConv() (in module mdf4reader), 36
read() (mdf3reader.DATA method), 18
read() (mdf4reader.DATA method), 30
read() (mdfreader.mdf method), 13
read3() (mdf3reader.mdf3 method), 20
read4() (mdf4reader.mdf4 method), 36
readATBlock() (mdfinfo4.info4 method), 45
readBitarray() (mdf4reader.record method), 38
readCGBBlock() (mdfinfo4.info4 method), 45
readCNBlock() (mdfinfo4.info4 method), 45
readComposition() (mdfinfo4.info4 method), 46
readDGBBlock() (mdfinfo4.info4 method), 46
readinfo() (mdfinfo4.info4 method), 46
readinfo() (mdfreader.mdfinfo method), 15
readinfo3() (mdfinfo3.info3 method), 26
readRecord() (mdf4reader.DATA method), 30
readRecordBuf() (mdf4reader.record method), 38
readSortedRecord() (mdf3reader.record method), 21
readSortedRecord() (mdf4reader.record method), 38

readSRBlock() (mdfinfo4.info4 method), 46
readUnsortedRecord() (mdf3reader.record method), 22
record (class in mdf3reader), 21
record (class in mdf4reader), 37
recordChannel (class in mdf3reader), 22
remove_channel() (mdf.mdf_skeleton method), 6
remove_channel_conversion() (mdf.mdf_skeleton method), 6
resample() (mdfreader.mdf method), 14

S

set() (mdf4reader.channel method), 33
setCANOpen() (mdf4reader.channel method), 33
setChannelAttachment() (mdf.mdf_skeleton method), 6
setChannelConversion() (mdf.mdf_skeleton method), 6
setChannelData() (mdf.mdf_skeleton method), 6
setChannelDesc() (mdf.mdf_skeleton method), 6
setChannelMaster() (mdf.mdf_skeleton method), 7
setChannelMasterType() (mdf.mdf_skeleton method), 7
setChannelUnit() (mdf.mdf_skeleton method), 7
setInvalidBytes() (mdf4reader.channel method), 33
SIBlock (class in mdfinfo4), 44
SRBlock (class in mdfinfo4), 44

T

tabConv() (in module mdf3reader), 22
tabInterpConv() (in module mdf3reader), 23
textRangeTableConv() (in module mdf3reader), 23
textToTextConv() (in module mdf4reader), 39
textToValueConv() (in module mdf4reader), 39

V

validity_channel() (mdf4reader.channel method), 34
valueRangeToTextConv() (in module mdf4reader), 39
valueRangeToValueTableConv() (in module mdf4reader), 39
valueToTextConv() (in module mdf4reader), 39
valueToValueTableWInterpConv() (in module mdf4reader), 39
valueToValueTableWOInterpConv() (in module mdf4reader), 40

W

write() (mdfreader.mdf method), 14
write3() (mdf3reader.mdf3 method), 20